

Latest software update for SPARC MGS and SPARC Sigma MGS owners

Your watch should have the software version v1.08, introduced in early May 2013, which automatically switches-off the system when the watch is not used for 50 hours. This prevents the accumulator to empty completely.

If you still have an earlier Version, please send your watch to one of the official Ventura Service centers indicated at "SERVICE, PARTS" to obtain a free-of-charge update.

The software v1.08 optimizes the EasySkroll switching by separating the sequences with a slight pause. If you experience frequent switching problems with the scroller, we recommend you to upgrade to v1.08.

How to check your current firmware version:

Switch off the system by pressing light button (first) and scroller simultaneously for 4 seconds and release; the display should now be blank (if not, repeat the procedure). Wait 2 - 3 minutes and press scroller once; all segments of the display will turn on and off again; then the Firmware version will briefly be shown.

Important: Usage of the v-winder

To recharge the accumulator of the watch with the v-winder, it is essential to switch off the system first (see procedure explained above).